

# ACTIVE FTP and PASSIVE FTP

## The Classic Definitive Explanation

### Introduction

One of the most commonly seen questions when dealing with firewalls and other Internet connectivity issues is the difference between active and passive FTP and how best to support either or both of them. Hopefully the following text will help to clear up some of the confusion over how to support FTP in a firewalled environment.

This may not be *the* definitive explanation, as the title claims; however, I've heard enough good feedback and seen this document linked in enough places to know that quite a few people have found it to be useful. I am always looking for ways to improve things though, and if you find something that is not quite clear or needs more explanation, please let me know! Recent additions to this document include the examples of both active and passive command line FTP sessions. These session examples should help make things a bit clearer. They also provide a nice picture into what goes on behind the scenes during an FTP session. Now, on to the information.

### The Basics

FTP is a TCP based service exclusively. There is no UDP component to FTP. FTP is an unusual service in that it utilizes two ports, a 'data' port and a 'command' port (also known as the control port). Traditionally these are port 21 for the command port and port 20 for the data port. The confusion begins however, when we find that depending on the mode, the data port is not always on port 20.

### Active FTP

In active mode FTP the client connects from a random unprivileged port ( $N > 1023$ ) to the FTP server's command port, port 21. Then, the client starts listening to port  $N+1$  and sends the FTP command PORT  $N+1$  to the FTP server. The server will then connect back to the client's specified data port from its local data port, which is port 20.


From the server-side firewall's standpoint, to support active mode FTP the following communication channels need to be opened:

- FTP server's port 21 from anywhere (Client initiates connection)
- FTP server's port 21 to ports  $> 1023$  (Server responds to client's control port)
- FTP server's port 20 to ports  $> 1023$  (Server initiates data connection to client's data port)
- FTP server's port 20 from ports  $> 1023$  (Client sends ACKs to server's data port)

When drawn out, the connection appears as follows:

## ACTIVE FTP and PASSIVE FTP

### The Classic Definitive Explanation



In step 1, the client's command port contacts the server's command port and sends the command PORT 1027. The server then sends an ACK back to the client's command port in step 2. In step 3 the server initiates a connection on its local data port to the data port the client specified earlier. Finally, the client sends an ACK back as shown in step 4.

The main problem with active mode FTP actually falls on the client side. The FTP client doesn't make the actual connection to the data port of the server--it simply tells the server what port it is listening on and the server connects back to the specified port on the client. From the client side firewall this appears to be an outside system initiating a connection to an internal client--something that is usually blocked.

### Active FTP Example

Below is an actual example of an active FTP session. The only things that have been changed are the server names, IP addresses, and user names. In this example an FTP session is initiated from testbox1.slacksite.com (192.168.150.80), a Linux box running the standard FTP command line client, to testbox2.slacksite.com (192.168.150.90), a Linux box running ProFTPD 1.2.2RC2. The debugging (-d) flag is used with the FTP client to show what is going on behind the scenes. Everything in **red** is the debugging output which shows the actual FTP commands being sent to the server and the responses generated from those commands. Normal server output is shown in black, and user input is in **bold**.

## ACTIVE FTP and PASSIVE FTP

### The Classic Definitive Explanation

There are a few interesting things to consider about this dialog. Notice that when the PORT command is issued, it specifies a port on the *client* (192.168.150.80) system, rather than the server. We will see the opposite behavior when we use passive FTP. While we are on the subject, a quick note about the format of the PORT command. As you can see in the example below it is formatted as a series of six numbers separated by commas. The first four octets are the IP address while the last two octets comprise the port that will be used for the data connection. To find the actual port multiply the fifth octet by 256 and then add the sixth octet to the total. Thus in the example below the port number is  $(14 * 256) + 178$ , or 3762. A quick check with netstat should confirm this information.

```
testbox1: {/home/p-t/slacker/public_html} % ftp -d testbox2
Connected to testbox2.slacksite.com.
220 testbox2.slacksite.com FTP server ready.
Name (testbox2:slacker): slacker
---> USER slacker
331 Password required for slacker.
Password: TmpPass
---> PASS XXXX
230 User slacker logged in.
---> SYST
215 UNIX Type: L8
Remote system type is UNIX.
Using binary mode to transfer files.
ftp> ls
ftp: setsockopt (ignored): Permission denied
---> PORT 192,168,150,80,14,178
200 PORT command successful.
---> LIST
150 Opening ASCII mode data connection for file list.
drwx----- 3 slacker users 104 Jul 27 01:45 public_html
226 Transfer complete.
ftp> quit
---> QUIT
221 Goodbye.
```

### Passive FTP

In order to resolve the issue of the server initiating the connection to the client a different method for FTP connections was developed. This was known as passive mode, or PASV, after the command used by the client to tell the server it is in passive mode.

In passive mode FTP the client initiates both connections to the server, solving the problem of firewalls filtering the incoming data port connection to the client from the server. When opening an FTP connection, the client opens two random unprivileged ports locally ( $N > 1023$  and  $N+1$ ). The first port contacts the server on port 21, but instead of then issuing a PORT command and allowing the server to connect back to its data port, the client will issue the PASV command. The result of this is that the server then opens a random unprivileged port ( $P > 1023$ ) and sends the PORT P command back to the client. The client then initiates the connection from port  $N+1$  to port  $P$  on the server to transfer data.


## ACTIVE FTP and PASSIVE FTP

### The Classic Definitive Explanation

From the server-side firewall's standpoint, to support passive mode FTP the following communication channels need to be opened:

- FTP server's port 21 from anywhere (Client initiates connection)
- FTP server's port 21 to ports > 1023 (Server responds to client's control port)
- FTP server's ports > 1023 from anywhere (Client initiates data connection to random port specified by server)
- FTP server's ports > 1023 to remote ports > 1023 (Server sends ACKs (and data) to client's data port)

When drawn, a passive mode FTP connection looks like this:



In step 1, the client contacts the server on the command port and issues the PASV command. The server then replies in step 2 with PORT 2024, telling the client which port it is listening to for the data connection. In step 3 the client then initiates the data connection from its data port to the specified server data port. Finally, the server sends back an ACK in step 4 to the client's data port.

While passive mode FTP solves many of the problems from the client side, it opens up a whole range of problems on the server side. The biggest issue is the need to allow any remote connection

## ACTIVE FTP and PASSIVE FTP

### The Classic Definitive Explanation

to high numbered ports on the server. Fortunately, many FTP daemons, including the popular WU-FTPD allow the administrator to specify a range of ports which the FTP server will use. See [Appendix 1](#) for more information.

The second issue involves supporting and troubleshooting clients which do (or do not) support passive mode. As an example, the command line FTP utility provided with Solaris does not support passive mode, necessitating a third-party FTP client, such as ncftp.

With the massive popularity of the World Wide Web, many people prefer to use their web browser as an FTP client. Most browsers only support passive mode when accessing ftp:// URLs. This can either be good or bad depending on what the servers and firewalls are configured to support.

### Passive FTP Example

Below is an actual example of a passive FTP session. The only things that have been changed are the server names, IP addresses, and user names. In this example an FTP session is initiated from testbox1.slacksite.com (192.168.150.80), a Linux box running the standard FTP command line client, to testbox2.slacksite.com (192.168.150.90), a Linux box running ProFTPD 1.2.2RC2.

The debugging (-d) flag is used with the FTP client to show what is going on behind the scenes. Everything in **red** is the debugging output which shows the actual FTP commands being sent to the server and the responses generated from those commands. Normal server output is shown in black, and user input is in **bold**.

Notice the difference in the PORT command in this example as opposed to the active FTP example. Here, we see a port being opened on the *server* (192.168.150.90) system, rather than the client. See the discussion about the format of the PORT command above, in the Active FTP Example section.

```
testbox1: {/home/p-t/slacker/public_html} % ftp -d testbox2
Connected to testbox2.slacksite.com.
220 testbox2.slacksite.com FTP server ready.
Name (testbox2:slacker): slacker
---> USER slacker
331 Password required for slacker.
Password: TmpPass
---> PASS XXXX
230 User slacker logged in.
---> SYST
215 UNIX Type: L8
Remote system type is UNIX.
Using binary mode to transfer files.
ftp> passive
Passive mode on.
ftp> ls
ftp: setsockopt (ignored): Permission denied
---> PASV
227 Entering Passive Mode (192,168,150,90,195,149).
---> LIST
150 Opening ASCII mode data connection for file list
drwx----- 3 slacker  users      104 Jul 27 01:45 public_html
```

# ACTIVE FTP and PASSIVE FTP

## The Classic Definitive Explanation

226 Transfer complete.

ftp> **quit**

---> **QUIT**

221 Goodbye.

### Other Notes

A reader, Maarten Sjouw, pointed out that active FTP will not function when used in conjunction with a client-side NAT (Network Address Translation) device which is not smart enough to alter the IP address info in FTP packets.

### Summary

The following chart should help admins remember how each FTP mode works:

Active FTP :

command : client >1023 -> server 21

data : client >1023 <- server 20

Passive FTP :

command : client >1023 -> server 21

data : client >1023 -> server >1023

A quick summary of the pros and cons of active vs. passive FTP is also in order:

Active FTP is beneficial to the FTP server admin, but detrimental to the client side admin. The FTP server attempts to make connections to random high ports on the client, which would almost certainly be blocked by a firewall on the client side. Passive FTP is beneficial to the client, but detrimental to the FTP server admin. The client will make both connections to the server, but one of them will be to a random high port, which would almost certainly be blocked by a firewall on the server side.

Luckily, there is somewhat of a compromise. Since admins running FTP servers will need to make their servers accessible to the greatest number of clients, they will almost certainly need to support passive FTP. The exposure of high level ports on the server can be minimized by specifying a limited port range for the FTP server to use. Thus, everything except for this range of ports can be firewalled on the server side. While this doesn't eliminate all risk to the server, it decreases it tremendously. See [Appendix 1](#) for more information.

## Appendix 1

### Introduction

This appendix will describe methods used to configure various popular FTP servers to limit the number of passive ports they will listen on. As mentioned in the main text, FTP server admins will almost definitely need to support passive FTP in order to allow the greatest number of clients to access their FTP resources. In order to support passive FTP, however, a large number of high-numbered ports on the server must be opened through a firewall. Luckily, most FTP servers allow this port range to be specified so as to limit exposure to attacks.

## ACTIVE FTP and PASSIVE FTP

### The Classic Definitive Explanation

#### ProFTPd

ProFTPd is an increasingly popular FTP server due to its modularity and Apache-style configuration directives. ProFTPd also supports virtual hosts "out of the box", causing it to become one of the most common FTP servers used by web hosting companies.

As of version 1.20RC3 and later (current version as of this writing is 1.2.4), ProFTPd supports a directive called PassivePorts. The PassivePorts directive is usually used in a global context in the proftpd.conf file (the location of which varies depending on how ProFTPd was configured and installed). PassivePorts takes two arguments, the minimum port number and the maximum port number, as in the below example:

#### PassivePorts 51000 51999

The ProFTPd documentation has the following to say about the PassivePorts directive:

PassivePorts restricts the range of ports from which the server will select when sent the PASV command from a client. The server will randomly choose a number from within the specified range until an open port is found. Should no open ports be found within the given range, the server will default to a normal kernel-assigned port, and a message logged.

The port range selected must be in the non-privileged range (eg. greater than or equal to 1024); it is **STRONGLY RECOMMENDED** that the chosen range be large enough to handle many simultaneous passive connections (for example, 49152-65534, the IANA-registered ephemeral port range).

If you are attempting to use SSH port forwarding to securely tunnel the FTP command channel over an SSH connection (so that passwords are not sent in clear text), be aware that you must set the AllowForeignAddress directive to "on" in the proftpd.conf file. If this is not set and a tunnelled connection is attempted, ProFTPd will log a message similar to the following:

**SECURITY VIOLATION: Passive connection from a.b.c.d rejected**

**Important Note: Please read and understand the documentation about the AllowForeignAddress directive before implementing it. This can open your FTP server up to bounce attacks. It is strongly recommended that this option not be set on systems being used as anonymous FTP servers.**